

Installing Amiga Explorer

- 1) Set up the Amiga Serial Port;
 - a. BAUD = 19200
 - b. Input buffer = 4096
 - c. Handshaking = RTS/CTS
 - d. Parity = None
 - e. Bits/Char = 8
 - f. Stop Bits = 1
 - g. Save the Settings

Follow "Amiga Explorer Setup Wizard" instructions.

In addition to the wizard, it will be necessary to transfer the "Amiga Explorer File and its Icon" to the Amiga. This can be done after a connection between computers is made. I usually install this file in the DH0: partition (System) and then move (or copy) it into the Workbench startup folder.

On the PC-C:Program Files/Cloanto/Amiga Explorer/Amiga/AExplorer

The two files that are created during the initial set up and transfer are enough to make the program work. But the two files are stored in RAM and will not be available if you restart the computer. It is necessary to have the Amiga Explorer tool on the Amiga to efficiently start the program.

You can save the AE file to any folder in the System Partition, but to start it up when the machine starts, put a copy in the WBStartup folder.

Remember that this tool starts on boot up, so if you want the Serial Port for another service, you will have to remove AE from the WBStartup.